

Installing the XRC-200 Data Backup Tool

The XRC-200 Data Backup Tool can be installed easily by following the instructions below. It is strongly recommended that you follow these procedures step-by-step.

1. System Requirements


Make sure, you have a PC available that meets the following requirements.

Operating System	Windows XP or a later version of Windows
USB Connection	1 available USB port + 1 standard USB cable
Hard Disk Space	At least 60 MB of free space

2. Installation of the XRC-200 Data Backup Tool

Download the XRC-200 Data Backup Tool by entering the URL http://www.swisson.com/downloads/XRC-200_DataBackupTool.zip in the address line of your web browser, if you haven't done this yet. Note that the URL is case sensitive. Extract the zip file and launch the installer executable 'Setup_XRC-200_DataBackupTool.exe'.

After accepting the license agreement, a dialog as depicted below will show up. Make sure the checkboxes 'Data Backup Tool' and 'Driver' are both ticked. Continue the setup by clicking 'Next' twice, then hit 'Install' and wait until the setup process is completed.



3. Using the XRC-200 Data Backup Tool

Click *Start>All Programs>Swisson XRC-200-Data Backup Tool>XRC-200 Data Backup Tool* to launch the Program. After starting the program, you may access the online manual via the menu item *Help>Manual*.

*SWISSON	XRC-200 Data Backup Tool		1
-----------------	---------------------------------	--	---